



REST API role remains in System Manager GUI even if it deleted from both CLI and GUI

https://kb.netapp.com/on-prem/ontap/Ontap_OS/OS-KBs/REST_API_role_remains_in_System_Manag...

Updated: Sun, 05 Apr 2026 20:39:54 GMT

Applies to

- ONTAP 9.17.1P2
- REST API
- System Manager

Issue

1. Rest API role (in case names **'test'**) created in the GUI with multiple priviledges assigned:

```
[kern_audit:info:3242] Vserver-01: http :: client-IP:65399 ::  
Vserver-01:admin:admin :: POST /api/security/roles : [{"X-Dot-Client-App:  
SMv4"} {"name":"test", "privileges":[{"access":"readonly", "path":"/api"}]}
```

```

:: Pending
[kern_audit:info:3242] Vserver-01: http :: client-IP:65399 ::
Vserver-01:admin:admin :: POST /api/security/roles : [{"X-Dot-Client-App:
SMv4"} {"name":"test","privileges":[{"access":"readonly","path":"/api"}]}
:: Success:
/api (readonly)
/api/security (readonly)
/api/security/authentication/password (all)
/api/security/authentication/publickeys (all)
...

```

2. A user (in case names '**user-01**') created then deleted from the GUI:

```

[kern_audit:info:3242] Vserver-01: http :: cluster-mgmt:50715 ::
Vserver-01:admin:admin :: PATCH /api/security/accounts/account-uuid/user-01
: [{"X-Dot-Client-App: SMv4"} {"applications":[{"application":"
http","authentication_methods":["password"],"second_authentication_method":"no
:: Pending
[kern_audit:info:3242] Vserver-01: http :: cluster-mgmt:50715 ::
Vserver-01:admin:admin :: PATCH /api/security/accounts/account-uuid/user-01
: [{"X-Dot-Client-App: SMv4"} {"applications":[{"application":"
http","authentication_methods":["password"],"second_authentication_method":"no
:: Success:
[kern_audit:info:3242] Vserver-01: http :: cluster-mgmt:58930 ::
Vserver-01:admin:admin :: PATCH /api/security/accounts/account-uuid/user-01
: [{"X-Dot-Client-App: SMv4"} {"password":***} :: Pending
[kern_audit:info:3242] Vserver-01: http :: cluster-mgmt:58930 ::
Vserver-01:admin:admin :: PATCH /api/security/accounts/account-uuid/user-01
: [{"X-Dot-Client-App: SMv4"} {"password":***} :: Success:
[kern_audit:info:3242] Vserver-01: http :: cluster-mgmt:63702 ::
Vserver-01:admin:admin :: DELETE /api/security/accounts/account-uuid/
user-01 : [{"X-Dot-Client-App: SMv4"} :: Pending
[kern_audit:info:3242] Vserver-01: http :: cluster-mgmt:63702 ::
Vserver-01:admin:admin :: DELETE /api/security/accounts/account-uuid/
user-01 : [{"X-Dot-Client-App: SMv4"} :: Success:

```

3. Then the role get deleted from the GUI:

```

[kern_audit:info:3242] Vserver-01: http :: cluster-mgmt:59811 ::
Vserver-01:admin:admin :: DELETE /api/security/roles/account-uuid/test :
[{"X-Dot-Client-App: SMv4"} :: Pending
[kern_audit:info:3242] Vserver-01: http :: cluster-mgmt:59811 ::
Vserver-01:admin:admin :: DELETE /api/security/roles/account-uuid/test :
[{"X-Dot-Client-App: SMv4"} :: Success:

```

4. Confirmed the role no longer exists in CLI output of ::>security login role show

5. However, the role **test** still remains in the GUI: (In case from **Cluster -> Settings -> User and Roles -> Roles**)

ルール

+ 追加



ルール



snaplock



test

コマンド

cluster log-forwarding

security anti-ransomware update-package-from-uri

security anti-ransomware volume

security audit log

security audit modify

security audit show

security certificate

9 個中 1 ~ 9



1

